

iX Capture 3.4.1 processing productivity benchmarks

Local internet connection speed (upload/download)	200 Mbps
Number of PhaseOne images	100
Image size (MP)	150
Volume of 100 images in IIQ format (GB)	13.6
Upload time for 100 images in IIQ format (min)	13
Volume of 100 images in TIFF format (GB)	42.2
Upload time for 100 images in TIFF format (min)	40
iX Capture conversion of 100 IIQ images to TIFF (min)	8

Recommendations to operate iX Capture:

If you have hundreds of images, to reach a maximal speed of conversion, proceed as following:

1. Start iX Capture
2. Select 3-5 images
3. Convert them to TIFF or JPEG
4. Stop conversion and delete history (CLEAR DONE) in iX Capture
5. Exit iX Capture
6. Start iX Capture again
7. Select all the images
8. Run conversion for all the images